

RoomWizard Administrative Console 1.0

September 27, 2012

Overview

This document describes updates for Steelcase's new RoomWizard Administrative Console application for the RW10 and RW II.

Note that the RW II needs to be running firmware version 4.1, and the RW10 needs to be running 3.5.2 in order to unlock all the features of the console.

What's in 1.0?

The RoomWizard Administrative console makes it easier manage your RoomWizards by allowing you to find, copy configurations, and monitor your RoomWizards remotely.

Feature	Description
Find all the RoomWizards on a network	The RoomWizard Administrative Console can find all RoomWizards on a specific subnet you specify, as long as the units are powered up and available on the network. RoomWizard II's must be running firmware version 4.1 or later to be found. RoomWizard 10's must be running firmware version 3.5.2 or later.
Free form grouping of RoomWizards	The RoomWizard Administrative Console lets you create and maintain groups of RoomWizards practically unlimited in size. You can have a single group with all of your RW's in it, or group them by building, floor, etc. Just drag and drop your RoomWizard's to the groups you've created.
Save and restore custom lists of RoomWizards	You can save and restore your custom RoomWizard groups, so you can change how you view your network depending on your needs.

Display configuration and properties	You can see various configuration information about your RoomWizards directly in the console along with properties of the units such as firmware version, network speed, IP, etc. You can view current status such as disk free space, CPU utilization and other information.
View web page, front panel of any device quickly and easily	You can view any unit's front panel or its admin web page directly from the Administrative console. Note that the front panel is only viewable on RoomWizard II's, and only if the option is enabled on the RoomWizard.
Push configuration out to other RoomWizards	Simply configure one RoomWizard as you like, set it as master, and replicate its configuration out to every other RoomWizard with one operation
Add security certificates to your RoomWizards	You can add security certificates to your RoomWizards directly from the RoomWizard Administrative Console without needing a special patch from Tech Support.
Password Protection	Access to the RoomWizard Administrative Console is password protected. The RoomWizard Administrative console's default password is "roomwizard". This can be changed in the Options dialog (View->Options).
View and search log files	You can view and search log files that are on the RoomWizards, as well as change the debug logging level of your RoomWizards.

Note you must be running RoomWizard II Firmware Version 4.1 or RW10 Firmware Version 3.5.2 in order to utilize The RoomWizard Administrative Console.

Documentation

Documentation for The RoomWizard Administrative Console is available online at:

<http://www.steelcase.com/roomwizard>

How to Install

To download The RoomWizard Administrative Console:

Go to <http://www.steelcase.com/roomwizard> and select the “support” link.

1. Run the Setup file on a Windows PC.
2. Answer the prompts.
3. Run The RoomWizard Administrative Console.

Known Issues and Release Notes

The RoomWizard Administrative Console only supports the English Language.

Support:

If you have questions or difficulties with the installation, Call Steelcase technical support at: 1.800.334.4922 or send an e-mail to: techsupport@steelcase.com

Located in Europe, Middle East or Africa?

Please call 00 800 0 1111 222 (toll-free) from Austria, Benelux, Scandinavia, France, Germany, Ireland, Italy, Portugal, Spain, Switzerland or the UK, or call 00 33 3 88 13 3636 from any other country. You could also send an e-mail to: servicedesk.emea@steelcase.com

The available languages for that region are: English